

# Collection System Code Flow

**main.cpp**  
Starts the system

Pass resource string identifying  
all the DAQs to connect to.

**DAQ\_Interface.cpp:  
daqBootstrap()**

**library**  
library.h/.cpp

Contains all global variables and  
functions used by all files.

(1)

**Initialize()**

Initializes the connection to the specified DAQ(s).  
This is called a session. The variable name that talks  
to the DAQs in the session is “driver” within the  
DAQ class. This connects to the DAQ(s) and sets  
parameters. Any low level parameter settings for  
DAQ(s) are and should be done here.

(2)

Begins the collection loop.

**collectDaqData()**

(3) Call collection cycle for DAQ(s).

**DAQ.cpp**

(4)

**continuousRawData()**

(9)

When a signal to shutdown the system is received  
(currently by pressing ‘e’ for end on the keyboard),  
the current data stored in the buffer is  
written to file and the session with the DAQ(s) is closed.

**Shutdown**

(5)

**writeDaqDataToFile()**

After X number of records are collected,  
index the data and associate with  
respective channels and write to file.

(6)

**CSV\_Output.cpp**



(7)

**Write to file**

The time length of a file is  
set in the config file in  
seconds. The current default  
is 60 seconds or 1 minute.

(8)

**Flush buffer**

Release memory used by buffer.  
The buffer stores the data that  
is currently being held in memory  
before being written to disk.

Collect X number of records.  
One record represents  
one second. Hence, collect  
the specified time length  
of a file to be created.

